

MEDIATEK

MT6757P MFNR Manual

2017/03



Content

- MFNR2.0 Flow Introduction
- MFNR2.0 Tool Operation Guide
- MFNR2.0 Tuning Guide

Content


- **MFNR2.0 Flow Introduction**
- MFNR2.0 Tool Operation Guide
- MFNR2.0 Tuning Guide

MFNR Flow Introduction

Objective


- Reduce luma/chroma noise by multi-frame blending
- V2.0 new feature: motion area noise refinement (MFB/MAR)

Flow




$N \cdot I_{raw}$:	Input RAW files. In MT6757P, $N=2 \sim 6$
$N \cdot I_{bfld}$:	Images prepared to do multi-frame blending
I_{mfb} :	Single blended Image
I_{afld} :	Image after post-processing
I_{output} :	Image after motion area refinement

MFNR Flow Introduction




1. Before NR

- Convert RAW to YUV format
- Noise pre-reduced to fit into MFB's capacity
- Remove impulse noise and bad pixels
- Relative Registers:
 - MFNR → BEFORE-UDM
 - MFNR → BEFORE-NBC
 - MFNR → BEFORE-NBC2



MFNR Flow Introduction




2. MFB (Multi-Frame Blending)

- Compound motion-compensated frames into one frame
 - Reduce noise without losing details
 - Work on both luma and chroma noise
- Relative Registers:
 - MFNR → MFB/MAR



MFNR Flow Introduction




3. ISP Post NREE


- Apply AFTER-NBC/EE/NBC2/HFG:
 - Reduce low-frequency noise in advance
 - Improve image sharpness
 - Add random fine noise, for boosting visually clarity

- Relative Registers:

- MFNR → AFTER-NBC
- MFNR → AFTER-EE
- MFNR → AFTER-NBC2
- MFNR → AFTER-HFG




MFNR Flow Introduction



4. Motion Area Refinement

- Apply stronger NR against motion area
 - Remove motion occlusion noise left in MFB stage
 - Improve visual continuity around the boundary of motion and static areas
- Relative Registers:
 - MFNR → MFB/MAR
 - MFNR → MAR-NBC
 - MFNR → MAR-EE
 - MFNR → MAR-NBC2
 - MFNR → MAR-HFG





Content

- MFNR2.0 Flow Introduction
- **MFNR2.0 Tool Operation Guide**
- MFNR2.0 Tuning Guide

MFNR Tool Operation Guide


■ Step1 (I): Load RAW files

- Hot Key: CTRL + R
- Make sure that all MFNR RAW files share the same name, followed by a serial number
- Only the first one(*-01.raw) needs to be selected
- JPG and SDBLK with same file name will also be loaded automatically




MFNR Tool Operation Guide

- Step1 (II): Load DAT Settings
 - Hot Key: CTRL + D
 - For loading pre-saved DAT file, make sure RAW is loaded at first




MFNR Tool Operation Guide

- Step2: Ensure MFNR flow is enabled
 - Menu -> ISPs -> ensure "Multi-Frame Noise Reduction" is checked
(If RAW is shot in MFNR mode, it'll auto-checked after RAW/JPG loaded, only confirmation needed)



MFNR Tool Operation Guide


- Step3: Registers Checking/Tuning
 - MFNR related parameters are congregated into 12 tabs in MFNR page (Please refer following "MFNR Tuning Guide" section for tuning)








MFNR Tool Operation Guide

■ Step4(I): Full Simulation

- In MFB/MIX tab, make sure all MFNR stages are checked.



- Press  Time: 0 sec button to run simulation (Hot Key: F2)


- Check the running status:  Time: 0 sec   Time: 0 sec   Time: 52.165 sec
Before Run Running Run Finished

- It takes about 4~12 minutes for full MFNR simulation.

MFNR Tool Operation Guide


■ Step4(II): Partial Simulation

- Once full simulation is done, some stages can be skipped in next run if no register in the stages been changed.
- **Ex:** If only AFTER-NBC/EE module are tuned since previous run, Before/ MFB can be skipped in next run.






MFNR Tool Operation Guide

- Step5: Result Images Checking
 - Results are saved in “Results\” folder located in the same folder as the RAW files
 - Following bitmap files would be generated after full simulation:



MFNR Tool Operation Guide


- Step6: Save tuning result as DAT file
 - For next time tuning & simulation
 - Hot Key: CTRL + T
 - Can also choose to save MFNR related modules only. (CTRL + M)
 - Suggest to name DAT file with ISO/camera sensor/IC for recognizing



MFNR Tool Operation Guide

- Step7: Merge Settings to “camera_isp_regs_XXX.h”

Please refer “Guideline_ISP_Reg_Header_File_Tool.pptx”



The screenshot shows the main window of the MFNR Tool. It has a 'Main Reg File' field at the top with a file path and a 'Check' button. Below this are several columns of settings:

- Register File:** Radio buttons for Write (selected), Read, Copy, and Write from DAT. A 'RUN' button is below.
- Module:** A list of modules with checkboxes: DBS, OBC, BNR BPC, BNR NR1, BNR PDC, RMM, RNR, SL2, UDM (checked), ANR, ANR2, CCR, HFG, EE, NR3D, MFB, and MIXER3.
- Profile:** A list of profiles with radio buttons: Preview, Video, Capture, MFNRBefore_Blend (selected), MFNRBefore_Blend_ZOOM1, MFNRBefore_Blend_ZOOM2, HDRVideo_VSS, HDRPreview, HDRPreview_VSS, HDRVideo, HDRCapture, AUTOHDR_Preview_VSS, AUTOHDR_Video, AUTOHDR_Preview, AUTOHDR_Capture, AUTOHDR_Video_VSS, zCAPMFNR_Before_Blend, EISVideo, EISPreview, EISHDR_Preview, EISAUTO_HDR_Video, and EISAUTO_HDR_Preview.
- Mode:** Radio buttons for Preview (selected), Capture, Video, SlimVideo1, SlimVideo2, Custom1, Custom2, Custom3, Custom4, and Custom5.
- ISO:** A list of ISO values with radio buttons: 100, 200, 400, 800 (selected), 1200, 1600, 2000, 2400, 2800, 3200, 4000, 4800, 5600, 6400, 7200, 8000, 8800, 9600, 11200, and 12800.

MFNR Tool Operation Guide



- Step8: Set frame-number in “camera_feature_para_imxXXXmipiraw.h”
 - Set *capture_frame_number* = *blend_frame_number* = 6 (max. frames)
 - Set *mfl_iso_th* = minimum MFNR enable ISO
 - There are 7 ISO thresholds for MFB frame-number mapping. Frame_num1~7 are individually mapping to iso_level1~7

```
// Gives N, for capturing N frames
capture_frame_number    : 6,
// Gives N, for N-frame blending. E.g.: N = 6, 6-frame blending, do blending 5 times.
blend_frame_number     : 6,
// Give 0 or 1, 0 for half size MC, 1 for full size MC
full_size_mc           : 1,
memc_bad_mv_range      : 255,
memc_bad_mv_rate_th    : 12707,
// The threshold of doing MFB or not
mfl_iso_th             : 200,
// iso range for adaptive frame number mechanism
iso_level1             : 200,
iso_level2             : 300,
iso_level3             : 400,
iso_level4             : 600,
iso_level5             : 800,
iso_level6             : 2000, // reserved for extension
iso_level7             : 2000, // reserved for extension
// at least to set blend frame number >= 2
frame_num1             : 2,
frame_num2             : 3,
frame_num3             : 4,
frame_num4             : 5,
frame_num5             : 6,
frame_num6             : 6,
frame_num7             : 6, // reserved for extension
```

Content

- MFNR2.0 Flow Introduction
- MFNR2.0 Tool Operation Guide
- **MFNR2.0 Tuning Guide**

MFLL Tuning Guide



MFB Strength Decision

- Proper MFB strength is around 20~28

Lower Strength:

Weak NR result in static area



MFB Strength = 8

Proper Strength:

(MAR will take care of the motion noise)



MFB Strength = 24

Higher Strength:

Ghost side-effect in motion area





MFB Strength = 40

MFB Strength Decision

- Set CLIP_TH1& CLIP_TH2 after MFB strength decided.
- $CLIP_TH1 = CLIP_TH2 = (MFB_Strength + 8) * 1.2$

MFB	
0	BLD FLT MODE
2	BLD FLT WT MODE1
1	BLD_FLT WT MODE2
45	BLD CLIP TH1
45	BLD CLIP TH2
5	BLD MAX WT
0	BLD BRZ EN

MFNR Tuning Guide



Before NR - STEP 1

- Calculate proper I_{bfbld} noise STD by MFB Strength

$$STD(I_{bfbld}) \approx \frac{MFB_Strength}{3} \quad (\text{Consider noise/details balance})$$


EX:

- $MFB_Strength=20 \Rightarrow STD(I_{bfbld}) = 20/3 \approx 6.67$
- $MFB_Strength=28 \Rightarrow STD(I_{bfbld}) = 28/3 \approx 9.33$

- Tune BEFORE-UDM & BEFORE-NBC to fit I_{bfbld} into the STD limitation.

Before NR - STEP2: UDM

- Please refer DM3.0 tuning guide for register tuning.
- When ISO increases:
 - Dial “EE Noise Level” up
 - Dial “Connectivity Detail” down
 - Dial “EE Strength-Detail” down
 - Dial “NR Strength” up




Before NR - STEP 3

- Before tuning BEFORE-NBC, set **Y HH/HL/L Detail** =64 to measure STD with NR off
- If the STD meets the formula in STEP1, no need to enable BEFORE-NBC



Stddev:(Y,Cb,Cr)=(9.27, 0.81, 0.47)



Before NR - STEP 4

- Set **Y HH/HL/L Detail** =0 (no blend to source), for checking pure NR result
- Adjust **Y/C Noise** NR, ensure that noises in flat region are all cleaned (include impulse noises)



Stddev:(Y,Cb,Cr)=(2.89, 0.24, 0.00)

MFB/MAR	MAR-NBC	MAR-NBC2	MAR-EE	MAR-HFG	BEFORE-UDM
BEFORE-NBC	BEFORE-NBC2	AFTER-NBC	AFTER-NBC2	AFTER-EE	AFTER-HFG

NBC

Luma Preserve NR

Strength HH Freq: 4

Strength HL Freq: 4

Strength Low Freq: 4

Threshold: 162

Edge Smooth

Strength: 4

Luma NR Gain

Y0: 16

Y1: 16

Y2: 12

Y3: 10

Color Bleeding Suppression

Strength: 92

Edge Preserve NR

Y HH Freq Detail: 0

Y HL Freq Detail: 0

Y LowFreq Detail: 0

Corner NR

☒ Corner NR

Strength: 28

C Strength: 48

Kernel Size

☐ Luma Size 2x

☒ Chroma Size 2x

Min: 5

Max: 5

Y Noise: 20

Y Noise Low Freq: 0

C Noise: 20

HighFreq Bound.: 2

Impulse NR

Detect Sensi.: 23


Strength: 5

Before NR - STEP 5


- Increase **Y HH/HL/L Detail** to add noise/detail back, till the STD meets the requirement of STEP1 formula.



Stddev:(Y,Cb,Cr)=(5.70, 0.34, 0.07)



MFNR Tuning Guide




MFB Quality Check

Checkpoint:


■ *!bfbld*

- Check if all images meets the STD requirement
- Check if brightness/color/ISO of all images are consistent
- Check mfnr_sim_log.txt, ensure base_idx makes sense



■ *!mfb*

- Ghost effect in motion area(kids, cars, sports, walkers, etc)
 - Decrease XXX_THH0~2 / Increase “n” value in MFB v2.0 Tuning Step2
 - Need to re-tune MFB/BeforeUDM/NBC by steps
- Too much noise => Check the MFB weighting Map
 - Tune BEFORE-NBC/NBC2
 - Increase YL2_THH2
 - Noise in motion area can be ignore here, MAR will take care later
 - Stronger corner Noise => BEFORE_NBC_LCE_GAIN2~3 / BEFORE_UDM_SL_Y2
 - Some slighter noise can also be handled by AFTER-NBC later
- Lack of details
 - Lower UDM N0 / Higher UDM HT/HD
 - If details exist, just a little blurry, it can be enhanced by AFTER-EE later





MFB Quality Check

- **Weighting Map (BLD_W_OU.bmp)**

- Keep higher MFB weighting in static region (map pixel value = $32 * \text{frame_number}$)
=>Adjust BEFORE-NBC/NBC2, higher YL2_THH2
- Keep lower weighting in moving region (map pixel value $\rightarrow 0$)
=>Lower YL2_THH0




MFNR Tuning Guide




Post NREE - NBC

- Objective: STD in static area \approx referenced photo
 - Similar to BEFORE-NBC tuning steps
 - **Y HH/HL/L Detail**: control noise level
 - **Y Noise / C Noise** should be smaller than BEFORE-NBC
- Reduce low-frequency noise
 - Raise **Kernel Size Min/Max**
 - Check **Luma/Chroma Size 2x**




Post NREE - SEEE

- Objective: Final sharpness of edge and details \approx referenced photo
 - By frequency: Adjust **Freq. Division EE**
 - By Edge index: Adjust **EE LUT**
- Suppress ringing side-effect
 - Dial down **Enhance Bound**
- Please refer [SEEE3.0 Tuning Guide] for advanced EE tuning



Post NREE - NBC2

- If still impulse noises left in static area(sometimes they are raised by AFTER-EE), alleviate them by **Impulse NR** in AFTER-NBC2
- Use **Edge Preserve NR** for low-frequency chroma noise reduction (ultra-low frequency chroma noise can be taken care by later SWNR if needed)





Before AFTER NR/EE



AFTER-NR

AFTER-EE

Post NREE - HFG

- Raise Noise STD to enhance visual clarity
 - Noise STD $\approx 0 \sim 16$

MFB/MAR	MAR-NBC	MAR-NBC2	MAR-EE	MAR-HFG	BEFORE-UDM
BEFORE-NBC	BEFORE-NBC2	AFTER-NBC	AFTER-NBC2	AFTER-EE	AFTER-HFG
HFC Luma					
8 Noise STD					





Noise STD = 0



Noise STD = 16

MFNR Tuning Guide



MAR Tuning


■ Goal:

- Motion noise left by MFB should be handled in MAR(Motion Area Refinement), to keep its noise level being consistent with the static area

■ Tuning Criteria:

- MAR NR/EE strength can be predicted by fine-tuned AFTER NR/EE setting
- MAR-NBC/NBC2: check the motion noise level is similar to neighboring static area after MAR
- MAR-EE: \approx After-EE

■ Partial Run Setup:




Stage Select (Unchecked=skip)

- ☐ Before Blend Stage
- ☐ MFP Stage
- ☐ After Blend Stage
- ☒ MAR Stage

MAR – Tuning Criteria


- MAR-NBC only works on motion area.
- Make sure STD of static and motion area are similar after MAR



MAR – Tuning

■ MAR-NR Suggestion:

- **Y/C Noise** $\approx (\text{MFB FrameNum})^{0.5} \times [\text{AFTER_NBC1 PTC/Y}]$
- **Y HH/HL/L Detail :**
 - $\approx (0.3 \sim 0.5) \times (\text{AFTER_NBC1})$
 - Adjust to align $\text{STD}(\text{I}_{\text{post}})$
- Other parameter:
 - $\approx (\text{AFTER_NBC1}/2)$



■ MAR_M1

- M1↑: Motion Noise↓;
Details between motion & static area ↓
- Suggest M1 value for 6-frame MFB: 96~160


MAR	
32	M0
160	M1
0	B0
255	B1
2	DT
1	Y EN
1	UV EN

MAR – Result


img_afbld_out__4032x3016_8d_s1.bmp



MFNR_A.bmp



MFNR Tuning Guide



ISO Adaptive Frame Number

- InMFNR v2.0, It's available to change frame number by shooting ISO
 - The more frame number, the better SNR of image
 - Low ISO: original noise is low, use less frame for shooting performance
 - High ISO: Gradually increase frame number for image quality

Comparison of different frame number MFNR result:



No blending




2-frame MFNR




6-frame MFNR

ISO Adaptive Frame Number – Image Quality




ISO Adaptive Frame Number – Image Quality



ISO Adaptive Frame Number – Performance

Shot-to-Shot Latency


Without ISO adaptive:
performance drops a lot when step over the MFNR threshold



ISO Adaptive Frame Number – Performance

Shot-to-Shot Latency

With ISO adaptive:
Shot-to-shot time changes smoothly across ISO



ISO Adaptive Frame Number – Simulation

- Set “Total Frame” value in tool for simulation

BEFORE-NBC	BEFORE-NBC2	AFTER-NBC	AFTER-NBC2	AFTER-EE	AFTER-HFG
MFB/MAR	MAR-NBC	MAR-NBC2	MAR-EE	MAR-HFG	BEFORE-UDM
Multi-Frame Low-Light		Stage Select (Unchecked=skip)			
<input type="text" value="6"/> Total Frames		<input checked="" type="checkbox"/> Before Blend Stage			
MFB		<input checked="" type="checkbox"/> MFP Stage			
<input type="text" value="0"/> BLD FLT MODE		<input checked="" type="checkbox"/> After Blend Stage			
		<input checked="" type="checkbox"/> MAR Stage			

ISO Adaptive Frame Number – Tuning

- Initially MFNR should be tuned with the highest frame number.
- Once frame number falls, **AFTER-NBC** and **MAR_M1** need to be revised to keep the noise level consistency
- MAR_M1:

$$\text{New_M1} = \text{M0} + (\text{Old_M1} - \text{M0}) \times (\text{New_FrameNum} - 1) / (\text{Old_FrameNum} - 1)$$

Ex: 6-frames down to 3-frames:

$$\text{New_M1} = 32 + (160 - 32) \times (3 - 1) / (6 - 1) = 83$$

MAR	
32	M0
160	M1
0	B0
255	B1
2	DT
1	Y EN
1	UV EN




MAR	
32	M0
83	M1
0	B0
255	B1
5	DT
1	Y EN
1	UV EN

ISO Adaptive Frame Number – Tuning (AFTER-NBC1)

→ **Y/C Noise** : $\text{NewValue} \approx \text{OldValue} \times (\text{OldFrameNum} / \text{NewFrameNum})^{0.5}$

→ **Y HH/HL/L Detail** : $\text{NewValue} \approx \text{OldValue} / (\text{OldFrameNum} / \text{NewFrameNum})^{(0.25 \sim 0.4)}$



EX: AFTER-NBC in **6-frame** MFNR:

Y HH Detail = 45

Y Noise = 8

Down to **3-frame** MFNR:

Y HH Detail = $45 / (6/3)^{0.25} = 38$

Y Noise = $8 \times (6/3)^{0.5} = 11$

→ FrameNum ↓ **Impulse NR** ↑



everyday genius